
Does Your Phone Even Have a Magnetometer? How to Check Before Installing a Compass App

Before you install a compass app, find out whether your phone actually has a magnetometer — the sensor that makes real compass navigation possible.

Author: Lubor Šimůnek · Published: August 26, 2026 · Travel

Online version: https://appstoryo.com/en/blog/does-your-phone-have-magnetometer



What Is a Magnetometer and Why Does It Matter?

A magnetometer is a tiny chip inside your phone that detects Earth's magnetic field. It is the hardware that every compass app depends on. Without it, no software — no matter how polished — can tell you which direction is north while you are standing still. The sensor is small, cheap to include in premium devices, but it is routinely left out of budget Android phones to cut manufacturing costs.

If you have ever opened a compass app and watched the needle spin uselessly, or noticed that your phone's Maps app only shows your direction when you are walking (never when you are stationary), you have likely encountered a phone without a magnetometer.

How to Check Whether Your Phone Has One

1. Look Up the Specs on GSMArena

Go to **gsmarena.com**, search for your exact phone model, and scroll down to the *Sensors* row. If you see **Compass**, **Magnetometer**, or **Geomagnetic sensor** listed, your phone has the hardware. If that row only shows accelerometer, gyroscope, and proximity sensor — but

no compass — it is absent.

2. Use a Sensor Diagnostic App

Apps like **CPU-Z** or **AIDA64** (both free on Android) list every sensor chip detected on your device. Open the Sensors tab and scan the list. A magnetometer will usually appear as *Magnetic Field Sensor* or similar. On iOS, every iPhone since the iPhone 3GS has included a magnetometer, so this is primarily a concern on Android.

3. Test It in Google Maps

Open Google Maps, tap the location button to center on your position, then stand completely still. If the blue direction cone adjusts as you rotate your body, you have a working magnetometer. If it only updates when you start walking — using your movement to guess heading — the sensor is missing or broken.

Signs Your Phone Lacks a Magnetometer

- The compass needle spins randomly or freezes in place.
- Directions in Maps only update while you are moving.
- Any compass app you install shows wildly inconsistent readings.
- The phone's settings menu has no compass calibration option.

What Compass Apps Actually Do Without the Sensor

When a magnetometer is absent, compass apps have two options: display nothing useful, or fake a heading using GPS. GPS-based heading works by comparing two consecutive position fixes — it calculates the direction you traveled between them. This is fine for navigation while driving or cycling, but it is completely useless when you are standing still, since there is no movement to measure. A stationary GPS heading is essentially a random number.

Some apps quietly fall back to this GPS method without telling you, giving the illusion of a working compass. This is dangerous if you are relying on the reading for actual navigation in the field.

Which Phones Have a Magnetometer?

Every iPhone, every Samsung Galaxy mid-range and flagship, Google Pixel, and most phones priced above roughly $150–$200 include a magnetometer as standard. The sensor is absent most often in entry-level Android devices — particularly sub-$150 phones from brands that aggressively cut component costs. If you are buying a new phone and compass functionality matters to you, confirm the sensor is listed before purchasing.

How NorthPin Handles Sensor Quality

NorthPin True North Compass (free, no ads) takes an honest approach to this problem. When it detects magnetic interference or an unreliable magnetometer signal, it shows a clear sensor quality warning rather than silently displaying a bad reading. The built-in interference

detector and µT meter let you see exactly how much magnetic noise is affecting your heading, and the calibration guide walks you through fixing soft-iron interference with a simple figure-eight motion.

On Android, NorthPin is available at Google Play. If the app detects that your device has no magnetometer at all, it will tell you directly rather than pretending to work.

What to Do If Your Phone Has No Magnetometer

Your options are limited but real. For casual navigation while moving, a GPS-based heading in Google Maps is adequate. For serious outdoor use — hiking, orienteering, travel — consider a dedicated hardware compass (they cost under $15) or upgrade to a phone that includes the sensor. A compass app without a magnetometer is not a compass; it is a direction estimator that only works when you are already moving.

Check your specs first, download **NorthPin** if your phone has the sensor, and navigate with confidence.

Frequently Asked Questions

Can an app add a compass to a phone without the sensor?

No. A magnetometer is hardware — a tiny three-axis magnetic field sensor. No software can conjure the reading. Apps on sensorless phones either estimate direction from GPS movement, which works only while you walk or drive, or simply display a decorative needle. If a listing promises a working compass for a phone with no magnetometer, it is at best a GPS heading display.

Does a phone case affect the magnetometer?

Cases with magnetic closures, MagSafe rings, or metal kickstands can skew readings by tens of degrees, and cheap magnetic car mounts are the worst offenders. If the interference warning keeps appearing, take the phone out of its case and recalibrate with the figure-eight motion — if the reading snaps back, the case was the culprit.

Cite as: Lubor Šimůnek (2026). *Does Your Phone Even Have a Magnetometer? How to Check Before Installing a Compass App*. AppStoryo, lapnito.cz s.r.o..
https://appstoryo.com/en/blog/does-your-phone-have-magnetometer
© 2026 lapnito.cz s.r.o.